

Software Archimede

Software installation manual



Dear Sirs,
for the installation process we kindly ask you to keep carefully to the following instructions:

Recommended system requirements:

Hardware

Pentium CPU 1Ghz (or higher)

Computer IBM compatible

System RAM 256 MB (or higher)

Hard disk Minimum 200 MB

Screen resolution 1024x768 (or higher)

Operating systems

Windows© 7



Windows© VISTA

Windows© XP SP2

Windows© 2000 Professional SP4

1

- **UNINSTALL AND REMOVE**
any previous versions of Archimede.
- **DOWNLOAD**
the file ArchimedeSetup.zip from the web page
<http://www.thermokey.it/Software.aspx>



2

- **EXTRACT**
the downloaded file ArchimedeSetup.zip.

Apertura di Archimede2016NewSetup_160225.zip



È stato scelto di aprire:

 **Archimede2016NewSetup_160225.zip**

tipo: Compressed (zipped) Folder (67,9 MB)


da: <http://www.thermokey.it>

Che cosa deve fare Firefox con questo file?

 Apirlo con Salva file Da ora in avanti esegui questa azione per tutti i file di questo tipo.

OK

Annulla



Strumenti cartelle compresse Archimede2016NewSetup_160225

File Home Condividi Visualizza Estrai

« Windows (C:) » Utenti » demarco » Download » Archimede2016NewSetup_160225 » Archimede2016NewSetup_160225


Nome	Tipo	Dimensione compres...	Protetto da...	Dimensione	Proporzione	Ultima modifica
Archimede	IrfanView ICO File	1 KB	No	3 KB	75%	01/03/2016 08:00
autorun	Informazioni di installazio...	1 KB	No	1 KB	11%	01/03/2016 08:06
eula thermokey	RTF (Rich Text Format)	116 KB	No	643 KB	83%	01/03/2016 08:03
readme	RTF (Rich Text Format)	13 KB	No	84 KB	86%	01/03/2016 08:06
Setup	Applicazione	69.354 KB	No	69.885 KB	1%	01/03/2016 07:25

5 elementi 1 elemento selezionato 68,2 MB

3

▪ INSTALLATION



Proceed with the installation by running the file Setup.exe (click on the “run as administrator”).



4

▪ **USER LICENSE**




Read the user license agreement and accept the terms of the contract license.



4.1


- **PROCEED WITH THE INSTALLATION**

Ending the software installation by accepting the terms of the user license of the CutePDF (software required for printing the data sheets).



5

- **RESTART THE PC**
Follow the installation process to the end, then restart the PC.




6

- **RUN THE SOFTWARE**

by means of the image on the desktop.

- **SERIAL NUMBER**

If no previous versions of Archimede were installed, the following window with your personal Serial Number will appear.



Archimede 2016 - Build #1

Insert the activation code to unlock the program



ThermoKey

Serial Number:

User Name

Company

Activation Code:

7

- **ASK THE ACTIVATION CODE**
Ask directly ThermoKey for your Activation Code by sending an e-mail to archimede@thermokey.com. with your Serial Number, your full company name and your e-mail address.
- **ENTER THE ACTIVATION CODE**
sent by ThermoKey per e-mail and click Activate.

Archimede 2016 - Build #1

 Insert the activation code to unlock the program

ThermoKey

Serial Number:

User Name

Company


Activation Code:

8


- **WELCOME IN ARCHIMEDE!**

Please check if the installed version is the last one clicking “Start” or click “Save” to close the windows and to start selection.



9

- **SELECT THE DESIRED LANGUAGE** from the menu.



Notes about software installation

In order to use ARCHIMEDE as Windows® User of the Users group, the Administrator must connect the complete control of the folder Archimede to the Users group.

Please check periodically the availability of any update by the TRUEUPDATE® service.

For any question or need of technical support while installing or using ARCHIMEDE please do not hesitate to contact our specialized staff at the following e-mail address:
archimede@thermokey.com

ThermoKey S.p.A.